

TBB Scenario Create User manual

This document is a generic User Guide document for use by TBB Scenario Create Program It provides guidance and template material which is intended to assist users of how to import or create scenarios. And add commands to a project

Installation:


The TBB app is a pre-installed software so a double clicks on the TBB Scenario Create.jar file will launch the application main screen

How to use the TBB application:

The TBB Scenario Create program main screen allows you to chose from two main options


1- Import an existing scenario file:

Importing an existing scenario to the TBB Scenario Create program can be done easily by first clicking on import scenario button form the main screen



Then a new window will appear this window will allow you to choose the file from your computer.


Chose the appropriate scenario file




Then click open which will load the scenario into the program

2- Creating new Scenario

Creating a new scenario can be done by pressing on the new scenario button from the main screen of the TBB Scenario Create



Then it will open the create scenario screen which will allow the user to add command, remove command or to move commands



Adding command can be easily done choosing from the command drop-down menu

1-

The drop-down command menu that allow the user to choose from a list of commands which are (Read text, pause, Display text, Start Repeat, End Repeat, skip button, User input, sound, reset buttons, Clear all cell Display, clear cell Display, Display cell pins, Display Character, Raise pin, Lower pins, Skip location)

Then pressing on add command button a message will pop out to add the command arguments. Adding the correct arguments to the command then pressing ok button it will appear on the command list

There is two ways you can add sound to the scenario

- Import an audio file from the computer
- record sound from the sound window that will pop up

Sound Selection



The dialog box titled "Sound Selection" contains a green question mark icon and the text "File Chosen" followed by "N/A". It features a button labeled "Choose existing sound file", a separator "--- OR ---", a text input field labeled "File name...", a button labeled "Start Recording", a button labeled "Stop Recording", and an "OK" button at the bottom.

2-

the command list is where all added commands is displayed. select any command and then press action buttons like Remove, move up and move down you can edit the command location or remove the commands.

Export the scenario to a text file to be used in the braille device is can be done by the Export Scenario button .Then a new window will appear this window will allow you to choose where you want to save the scenario file in your computer.

